

ISY WinMap 2018 install

ISY WinMap is a complete solution for managing and updating of geographical information. The solution is built on GeoMedia desktop from Hexagon Geospatial. This version runs on GeoMedia Desktop 2018 (Version 16.5)

This installation guide is aimed for persons that will install the product via automated techniques. The document references usage of batch scripts that are delivered with the setup media.

For instructions of manual uninstall/install please refer to the document [ISYWinMap_Installasjon.pdf](#) (in Norwegian).

For detailed information on parameters for silent uninstall/install, please refer to the document [Silent setup ISY WinMap.pdf](#) in the Dok folder.

Important notes

- User to run install has to be logged on to the system with administrator privileges.
- Elevated privileges are required to run installs, equivalent to setting User Account control (UAC) to the lowest level during install. Normally the computer must be restarted for changes in UAC to effectuate.
- All installations have to be run As Administrator, i.e. right-click on the script file and select "Run as administrator".

Installation steps in short:

1. Make sure the user running the install has [elevated privileges](#).
2. [Download](#) the zip-file from <https://www.nois.no/nedlasting/isy-winmap1/#ISY-WinMap-2018-Svensk-version>.
3. Unblock the zip file and unzip it on a local folder. Copy to a server location if desirable.
4. Move the file [WinMap 2017 silent uninstall script.bat](#) to the folder where WinMap 2017 installation files reside.
5. Run the file [WinMap 2017 silent uninstall script.bat](#) as administrator to [uninstall previous version](#).
6. [Edit the configuration](#) files [license.txt](#), [licenseserver.txt](#) and [WinMap_job_settings.reg](#) in the Config folder.
7. Run the file [WinMap 2018 silent install.bat](#) to [install ISY WinMap 2018](#).
8. Verify log file.

Important details follow in sections below.

Download and unzip zip-file

ISY WinMap 2018 is downloaded from: <https://www.nois.no/nedlasting/isy-winmap1/#ISY-WinMap-2018-Svensk-version>.

Download the zip-file to a local disc, unblock it and unzip it. For performance reasons it's recommended that the zip file is unzipped at a local disk before copying the contents to a server location. Do not modify the structure of the unzipped files. There are strong relationships to this structure in the installation script files.

Uninstall previous versions

ISY WinMap 2018 is based on GeoMedia 2018, and thus earlier version must be uninstalled before installing this version. It is performed by uninstalling all ISY WinMap products, and then uninstall Hexagon GeoMedia desktop.

Uninstalling ISY WinMap 2017 can be done by running the script [WinMap 2017 silent uninstall script.bat](#) delivered with the installation. Please note: **This script is dependent on the ISY WinMap 2017 installation files**. So either...

- Move [WinMap 2017 silent uninstall script.bat](#) to the WinMap 2017 setup files folder and run it from there. (Recommended)
- or...
- Run the [WinMap 2017 silent uninstall script.bat](#) script with a parameter specifying the path to the WinMap 2017 setup files folder.
E.g. "[WinMap 2017 silent uninstall script.bat](#)" "\\Installationpath\WinMap2017". NB! If a server folder is used, it must be specified as an UNC path.

Edit configuration files

Go to the Config folder.

1. Edit [license.txt](#) to contain your organisation name, customer id and license number. Default content is:

```
Kommunnamn
90126
4-5649J-4948E-5749C-51540-00014
sv
landmaaling
```

Substitute the first three lines with your organisation name, customer number and license code.

The 4:th row states language ('sv' = Swedish) and should not be changes for Swedish customers. If the language is 'sv' the default components to be installed are ISY Winmap Commands, ISY WinMap Jobbhandtering, IYS WinMap Koordinattransformasjon and ISY WinMap Sosi GDO.

The 5:th line states additional ISY WinMap Products to be installed in addition to the default components. Separate those with a space or a comma. To install both "Fältmätning" and the "old" PostGISGDO-dataserver the 5:th line can look like this:

landmaaling, postgis

2. Edit the file [WinMap_job_settings.reg](#) to match the correct settings for your organisation. Refer to the document [Configure WinMap_job_settings_reg.pdf](#) for explanations of the different keys.

3. Edit the `licenseserver.txt` file to contain the name or ip-address to your license in order to have this configured during install. The file is only to contain the name or IP address of the server. The file delivered with the install contains license server IP for Södertörn: 10.91.100.20.
NB! No line break after the address!

Install

Important!!! Verify the configuration files are edited for your organisation as described above!!!

Then (as an administrator):

- **Run the script `WinMap 2018 silent install script.bat`** (recommended)

or...

- Run the script `WinMap 2018 silent install script.bat` with a parameter to specify the path to the installation file directory.
E.g. "`WinMap 2018 silent install script.bat`" "`\\installationpath\WinMap2018`". NB! If a server folder is used, it must be specified as an UNC path.

This will start the installation process of ISY WinMap 2018 (including both GeoMedia Desktop and all the ISY WinMap products) and it will take a while (approximately +15 minutes depending on network performance) during which several dialogs display and close.

If all works as expected no action is required from the user. When the installation is complete all installation windows and dialogs are closed, and all is calm 😊

Installation log

A log file with the name `WinMap2018_Install_<date>.log` is created in the `%temp%`-directory. Review it to verify the installation has been successful.

Report any issues to ISY Servicedesk (<https://sgd.astando.se:8443/redmine/projects/isy-support/issues/new>).

Good luck