

## Configure WinMap\_job\_settings.reg

2018-12-04

The file *WinMap\_job\_settings.reg* needs to be configured with the own municipality's settings before running the installation batch script.

Below is a list of what keys that normally needs to be edited.

[HKEY\_CURRENT\_USER\Software\NOIS\Commands\GeoProcessSettings]

Key	Value in WinMap_job_settings.reg	Configure to
GeoWorkspaceFolder	C:\GeoWorkspaces\SGD\Jobb	Own standard base directory for job-GeoWorkspaces
GeoworkspaceTemplateFolder	\\\\10.91.100.12\sgd\WinMap\Mallar\GeoWorkspaces	
LibraryFolder	C:\GeoWorkspaces\Libraries	
LayoutTemplateFolder	\\\\10.91.100.12\sgd\WinMap\Mallar\Layouts	
EnterpriseDatabaseName	NOEnterpriseJobs	
EnterpriseDatabaseServer	10.91.100.21	
EnterpriseDatabaseType	1	
EnterpriseUsername	EnterpriseBase	
EnterprisePassword	&A)4={61)})#)G)#)U{Z})&p)@{Z})	
MunicipalityName	Botkyrka	The own municipality name
KLM	FALSE	TRUE if the municipality is a KLM-municipality.
UseradminUrl	http://10.91.100.20/useradmin/service.asmx	
UserAdminUsername	slaps	
UserAdminPassword	{1)4#)6%)=)Y)})#{C)@)})#CAC#	
FIRURL	http://10.91.100.20/isyfir/sgd/v1/	
Fastighetsdatabase	Fastigheter	In some cases Fastighetskartan
MunicipalityNr	0127	The own municipality number
EPSGKode	3011	
FastighetPointFeature	FAST_GRANSPUNKT_P	
FastighetLineFeature	FAST_FASTIGHETSGRANS_L	
PresicionFieldName	lagesosakerhet_plan	
PresicionFieldHName	lagesosakerhet_hojd	
MeasureMethodFieldName	insamlingsmetod_plan	
MeasureMethodFieldHName	insamlingsmetod_hojd	

[HKEY\_CURRENT\_USER\Software\VB and VBA Program Settings\NOIS CustPrpDlg\CustPrpDlg]

Key	Value in WinMap_job_settings.reg	Configure to
Use	1	